


```

LL          XX      XX      CCCCCCCC      000000      MM      MM
LL          XX      XX      CCCCCCCC      000000      MM      MM
LL          XX      XX      CC              00          00      MMMM      MMMM
LL          XX      XX      CC              00          00      MMMM      MMMM
LL          XX      XX      CC              00          00      MM      MM      MM
LL          XX      XX      CC              00          00      MM      MM      MM
LL          XX      XX      CC              00          00      MM      MM      MM
LL          XX      XX      CC              00          00      MM      MM      MM
LL          XX      XX      CC              00          00      MM      MM      MM
LL          XX      XX      CC              00          00      MM      MM      MM
LL          XX      XX      CC              00          00      MM      MM      MM
LL          XX      XX      CC              00          00      MM      MM      MM
LLLLLLLLLLLLLXX      XX      CCCCCCCC      000000      MM      MM
LLLLLLLLLLLLLXX      XX      CCCCCCCC      000000      MM      MM

```

```

LL               IIIIII             SSSSSSSS
LL               IIIIII             SSSSSSSS
LL               II                 SS
LL               II                 SS
LL               II                 SS
LL               II                 SS
LL               II                 SSSSSS
LL               II                 SSSSSS
LL               II                 SS
LL               II                 SS
LL               II                 SS
LL               II                 SS
LLLLLLLLLLLLLL  IIIIII             SSSSSSSS
LLLLLLLLLLLLLL  IIIIII             SSSSSSSS

```



```
0001 0 %TITLE 'EDT$LXCOM - execute a line-mode command'
0002 0 MODULE EDT$LXCOM ( ! Execute a line-mode command
0003 0 IDENT = 'V04-000' ! File: LXCOM.BLI Edit: JBS1020
0004 0 ) =
0005 1 BEGIN
0006 1
0007 1 *****
0008 1 *
0009 1 * COPYRIGHT (c) 1978, 1980, 1982, 1984 BY *
0010 1 * DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS. *
0011 1 * ALL RIGHTS RESERVED. *
0012 1 *
0013 1 * THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED *
0014 1 * ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE *
0015 1 * INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER *
0016 1 * COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY *
0017 1 * OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY *
0018 1 * TRANSFERRED. *
0019 1 *
0020 1 * THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE *
0021 1 * AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT *
0022 1 * CORPORATION. *
0023 1 *
0024 1 * DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS *
0025 1 * SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL. *
0026 1 *
0027 1 *
0028 1 *****
0029 1
0030 1
0031 1 ++
0032 1 FACILITY: EDT -- The DEC Standard Editor
0033 1
0034 1 ABSTRACT:
0035 1
0036 1 Execute a line-mode command. Most of the work is done by external routines.
0037 1
0038 1 ENVIRONMENT: User mode
0039 1
0040 1 AUTHOR: Bob Kushlis, CREATION DATE: February 3, 1978
0041 1
0042 1 MODIFIED BY:
0043 1
0044 1 1-001 - Original. DJS 10-MAR-81. This module was created by
0045 1 extracting the routine EDT$$LNM_CMD from EXEC.BLI.
0046 1 1-002 - Fix module name. JBS 23-Mar-1981
0047 1 1-003 - Make sure the routine names start with EDT$$$. JBS 31-Mar-1981
0048 1 1-004 - Use the ASSERT macro. JBS 01-Jun-1981
0049 1 1-005 - Use the new message codes. JBS 04-Aug-1981
0050 1 1-006 - Add a synonym for the entry point name, so the overlay analyzer
0051 1 can be told to ignore it, and make sure the EXTEND module
0052 1 is in memory before returning. JBS 12-Mar-1982
0053 1 1-007 - Revise the overlay structure, since the method outlined above
0054 1 can cause an undefined symbol. JBS 15-Mar-1982
0055 1 1-008 - Remove the reference to EDT$$LOAD_EXTEND. JBS 18-Mar-1982
0056 1 1-009 - Set stay flag if command is a write. STS 10-May-1982
0057 1 1-010 - Bypass EDT$$LNM_HLP by calling EDT$$OUT_HLP directly. JBS 03-Jun-1982
```

EDT\$LXCOM
V04-000

EDT\$LXCOM - execute a line-mode command

C 3
16-Sep-1984 01:05:10
14-Sep-1984 12:23:47

VAX-11 Bliss-32 V4.0-742
DISK\$VMSMASTER:[EDT.SRC]LXCOM.BLI;1

Page 2
(1)

:	58	0058	1	:	1-011	- Set EDT\$\$G TXT_ONSCR for commands that don't. SMB 11-Jun-1982
:	59	0059	1	:	1-012	- Set stay flag if command is a print. STS 10-May-1982
:	60	0060	1	:	1-013	- Modify the setting of message flags. SMB 23-Jun-1982
:	61	0061	1	:	1-014	- Use EDT\$\$FMT CRLF instead of EDT\$\$OUT FMTBUF. This means we don't have
:	62	0062	1	:		to set EDT\$\$G MSGFLG or EDT\$\$G TXT_ONSCR in most cases. JBS 05-Jul-1982
:	63	0063	1	:	1-015	- Move setting of EDT\$\$G SCR_CHGD to the routines called. JBS 07-Jul-1982
:	64	0064	1	:	1-016	- Set EDT\$\$G SCR_CHG in FIND only if it succeeds. JBS 07-Jul-1982
:	65	0065	1	:	1-017	- Remove EDT\$\$G SCR_CHGD, the new screen logic does not need it. JBS 09-Oct-1982
:	66	0066	1	:	1-018	- Put code for edt\$\$rng_posfrst in line. STS 11-Oct-1982
:	67	0067	1	:	1-019	- Remove forced setting of G TXT_ONSCR for insert and replace. SMB 14-Dec-1982
:	68	0068	1	:	1-020	- Correct a typo in a comment. JBS 02-May-1983
:	69	0069	1	:	--	
:	70	0070	1	:		

EDT\$LXCOM
04-000

EDT\$LXCOM - execute a line-mode command
Declarations

D 3
16-Sep-1984 01:05:10
14-Sep-1984 12:23:47

VAX-11 Bliss-32 V4.0-742
DISK\$VMSMASTER:[EDT.SRC]LXCOM.BLI;1

Page 3
(2)

```

72 0071 1 %SBTTL 'Declarations'
73 0072 1
74 0073 1 | TABLE OF CONTENTS:
75 0074 1 |
76 0075 1
77 0076 1 REQUIRE 'EDTSRC:TRAROUNAM';
78 0515 1
79 0516 1 FORWARD ROUTINE
80 0517 1 EDT$$LNM_CMD : NOVALUE; ! Execute the last parsed command
81 0518 1
82 0519 1
83 0520 1 | INCLUDE FILES:
84 0521 1 |
85 0522 1
86 0523 1 REQUIRE 'EDTSRC:EDTREQ';
87 0658 1
88 0659 1
89 0660 1 | MACROS:
90 0661 1 |
91 0662 1 | NONE
92 0663 1 |
93 0664 1 | EQUATED SYMBOLS:
94 0665 1 |
95 0666 1 | +
96 0667 1 | The EXTEND change-mode command uses this symbol indirectly to refer
97 0668 1 | to this module, so the reference can be excluded from
98 0669 1 | the overlay analysis.
99 0670 1 | -
100 0671 1
101 0672 1 GLOBAL BIND
102 0673 1 ROUTINE
103 0674 1 EDT$$LNM_CMD_NOOVERLAY_REF = EDT$$LNM_CMD;
104 0675 1
105 0676 1 |
106 0677 1 | OWN STORAGE:
107 0678 1 |
108 0679 1 | NONE
109 0680 1 |
110 0681 1 | EXTERNAL REFERENCES:
111 0682 1 |
112 0683 1 | In the routines
```

```
114 0684 1 %SBTTL 'EDT$SLNM_CMD - execute a line-mode command'
115 0685 1
116 0686 1 GLOBAL ROUTINE EDT$SLNM_CMD (           ! Execute a line-mode command
117 0687 1     COM_START                          ! Command to execute
118 0688 1     ) : NOVALUE =
119 0689 1
120 0690 1 ++
121 0691 1 FUNCTIONAL DESCRIPTION:
122 0692 1
123 0693 1     This routine executes the command which was last parsed.
124 0694 1     It is assumed that the command is described in the first
125 0695 1     node on the parsing stack.
126 0696 1
127 0697 1 FORMAL PARAMETERS:
128 0698 1
129 0699 1     COM_START          Node block containing the command to execute
130 0700 1
131 0701 1 IMPLICIT INPUTS:
132 0702 1
133 0703 1     EDT$G_RCOV_MOD
134 0704 1     EDT$Z_PA_STK          The semantic stack containing the command to be executed
135 0705 1
136 0706 1 IMPLICIT OUTPUTS:
137 0707 1
138 0708 1     EDT$G_EDIT_MOD
139 0709 1     EDT$A_EXE_CURCMD
140 0710 1     EDT$Z_EXE_SBLK
141 0711 1     EDT$G_EXE_SBITS
142 0712 1     EDT$G_EXE_QRYQUIT
143 0713 1     EDT$G_EXITD
144 0714 1     EDT$G_TXT_ONSCR
145 0715 1
146 0716 1 ROUTINE VALUE:
147 0717 1
148 0718 1     NONE
149 0719 1
150 0720 1 SIDE EFFECTS:
151 0721 1
152 0722 1     MANY
153 0723 1
154 0724 1 --
155 0725 1
156 0726 2 BEGIN
157 0727 2
158 0728 2 EXTERNAL ROUTINE
159 0729 2     EDT$SC_NONREVID,
160 0730 2     EDT$STOP_WKINGMSG,
161 0731 2     EDT$CLR_CMD : NOVALUE,
162 0732 2     EDT$DEFK_CMD : NOVALUE,
163 0733 2     EDT$DEFM_CMD : NOVALUE,
164 0734 2     EDT$DEL_CMD : NOVALUE,
165 0735 2     EDT$MAC_CALL,
166 0736 2     EDT$EXI_CMD : NOVALUE,
167 0737 2     EDT$FIL_CMD : NOVALUE,
168 0738 2     EDT$FMT_CRLF,
169 0739 2     EDT$FMT_MSG,
170 0740 2     EDT$OUT_HLP,
171
172 ! Turn off reverse video
173 ! Turn off timer AST
174 ! Process the CLEAR command
175 ! Process the DEFINE KEY command
176 ! Process the DEFINE MACRO command
177 ! Process the DELETE command
178 ! Invoke a macro
179 ! Process the EXIT command
180 ! Process the FILL command
181 ! Terminate a line
182 ! Put the text of a message in the format buffer
183 ! Get help
```


EDT\$LXCOM
V04-000

EDT\$LXCOM - execute a line-mode command
EDT\$SLNM_CMD - execute a line-mode command

F 3

16-Sep-1984 01:05:10
14-Sep-1984 12:23:47

VAX-11 Bliss-32 V4.0-742
DISK\$VMSMASTER:[EDT.SRC]LXCOM.BLI;1

Page 5
(3)

```

: 171      0741 2      EDT$INCL_CMD : NOVALUE,      ! Process the INCLUDE command
: 172      0742 2      EDT$INS_CMD : NOVALUE,      ! Process the INSERT command
: 173      0743 2      EDT$DEL_LNS,      ! Delete a range of lines
: 174      0744 2      EDT$INS_TXT : NOVALUE,      ! Insert text
: 175      0745 2      EDT$MOVCPY_CMD : NOVALUE,      ! Process the MOVE and COPY commands
: 176      0746 2      EDT$NULL_CMD : NOVALUE,      ! Process the null command
: 177      0747 2      EDT$PRNT_CMD : NOVALUE,      ! Process the PRINT command
: 178      0748 2      EDT$RNG_REPOS,
: 179      0749 2      EDT$RSEQ_CMD : NOVALUE,      ! Process the RESEQUENCE command
: 180      0750 2      EDT$SET_CMD : NOVALUE,      ! Process the SET command
: 181      0751 2      EDT$SHW_CMD : NOVALUE,      ! Process the SHOW command
: 182      0752 2      EDT$LN_SUBCMD : NOVALUE,      ! Process the SUBSTITUTE command
: 183      0753 2      EDT$SUB_NXTCMD : NOVALUE,      ! Process the SUBSTITUTE NEXT command
: 184      0754 2      EDT$TSADJ_CMD : NOVALUE,      ! Process the TABS ADJUST command
: 185      0755 2      EDT$TY_CMD : NOVALUE,      ! Process the TYPE command
: 186      0756 2      EDT$WR_CMD : NOVALUE;      ! Process the WRITE command
: 187      0757
: 188      0758
: 189      0759      EXTERNAL
: 190      0760      EDT$G_EDIT_MOD,
: 191      0761 2      EDT$G_RCOV_MOD,
: 192      0762 2      EDT$G_TXT_ONSCR,      ! Use 'Press return to continue' after this command is done
: 193      0763 2      EDT$G_EXITD,
: 194      0764 2      EDT$A_EXE_CURCMD : REF NODE_BLOCK,      ! Pointer to the current command.
: 195      0765 2      EDT$G_EXE_QRYQUIT,      ! Quit flag for /QUERY operations.
: 196      0766 2      EDT$G_RNG_FRSTLN,
: 197      0767 2      EDT$A_CUR_BUF : REF TBCB_BLOCK,
: 198      0768 2      EDT$Z_RNG_ORIGPOS : POS_BLOCK,
: 199      0769 2      EDT$G_EXE_SBITS,      ! The options switches.
: 200      0770 2      EDT$Z_EXE_SBLK : REF NODE_BLOCK;      ! The option switch value block.
: 201      0771
: 202      0772      MESSAGES ((INVOPCOM));
: 203      0773 2      !+ Define the table containing valid options for each command.
: 204      0774 2      !-
: 205      0775
: 206      0776      BIND
: 207      0777      OPT_TABLE = UPLIT (BYTE (
: 208      0778      0,      ! Options for null command
: 209      0779      0,      ! Options for change
: 210      0780      OPT_DUPL+OPT_QUERY,      ! Options for copy
: 211      0781      0,      ! Options for define
: 212      0782 2      OPT_QUERY,      ! Options for delete
: 213      0783 2      OPT_SAVE+OPT_SEQ,      ! Options for exit
: 214      0784 2      0,      ! Options for find
: 215      0785 2      0,      ! Options for include
: 216      0786 2      0,      ! Options for insert
: 217      0787 2      OPT_QUERY,      ! Options for move
: 218      0788 2      0,      ! Options for print
: 219      0789 2      OPT_SAVE,      ! Options for quit
: 220      0790 2      0,      ! Options for replace
: 221      0791 2      OPT_SEQ,      ! Options for resequence
: 222      0792 2      0,      ! Options for set
: 223      0793 2      0,      ! Options for show
: 224      0794 2      OPT_QUERY+OPT_NOTYP+
: 225      0795 2      OPT_BRIEF,      ! Options for SUBSTITUTE
: 226      0796 2      OPT_BRIEF+OPT_STAY,      ! Options for type
: 227      0797 2      OPT_SEQ,      ! Options for write
```

EDT\$LXCOM
V04-000

EDT\$LXCOM - execute a line-mode command
EDT\$SLNM_CMD - execute a line-mode command

6 3
16-Sep-1984 01:05:10
14-Sep-1984 12:23:47

VAX-11 Bliss-32 V4.0-742
DISK\$VMSMASTER:[EDT.SRC]LXCOM.BLI;1 Page 6
(3)

```

228      0798      2      0,      | Options for subs next
229      0799      2      0,      | Options for help
230      0800      2      OPT_NOTYP, | Options for verify
231      0801      2      0,      | Options for tab adjust
232      0802      2      0,      | Options for fill
233      0803      2      0,      | Options for def macro
234      0804      2      0,      | Options for mac call
235      0805      2      )): VECTOR [LAST_COM, BYTE];
236      0806
237      0807      2      EDT$A_EXE_CURCMD = .COM_START;
238      0808      2      +
239      0809      2      - The top level had better be a command code.
240      0810
241      0811      2      ASSERT (.EDT$A_EXE_CURCMD [NODE_TYPE] EQL COM_NODE);
242      0812      2      EDT$Z_EXE_SBLK = .EDT$A_EXE_CURCMD [SWITS];
243      0813
244      0814      2      IF (.EDT$Z_EXE_SBLK NEQ 0)
245      0815      2      THEN
246      0816      2      BEGIN
247      0817      2      IF ((.EDT$Z_EXE_SBLK [SW_BITS] AND ( NOT .OPT_TABLE [.EDT$A_EXE_CURCMD [COM_NUM]])) NEQ 0)
248      0818      2      THEN
249      0819      2      BEGIN
250      0820      2      EDT$FMT_MSG (EDT$_INVOPCOM);
251      0821      2      RETURN;
252      0822      2      END;
253      0823
254      0824      2      EDT$G_EXE_SBITS = .EDT$Z_EXE_SBLK [SW_BITS];
255      0825      2      END
256      0826      2      ELSE
257      0827      2      EDT$G_EXE_SBITS = 0;
258      0828
259      0829      2      EDT$G_EXE_QRYQUIT = 0;
260      0830
261      0831      2      CASE .EDT$A_EXE_CURCMD [COM_NUM] FROM COM_NULL TO LAST_COM OF
262      0832      2      SET
263      0833      2      [COM_QUIT] :
264      0834      2      BEGIN
265      0835      2      EDT$G_EXITD = 1;
266      0836      2      EDT$FMT_CRLF ();
267      0837      2      END;
268      0838
269      0839      2      [COM_INSERT] :
270      0840      2      BEGIN
271      0841      2      EDT$INS_CMD ();
272      0842      2      END;
273      0843
274      0844      2      [COM_DELETE] :
275      0845      2      BEGIN
276      0846      2      EDT$DEL_CMD ();
277      0847      2      END;
278      0848
279      0849      2      [COM_TYPE] :
280      0850      2      BEGIN
281      0851      2      EDT$STOP_WKINGMSG ();
282      0852      2      EDT$SC_NONREVID ();
283      0853
284      0854
```


EDTSLXCOM
V04-000

EDTSLXCOM - execute a line-mode command
EDTSSLNM_CMD - execute a line-mode command

H 3
16-Sep-1984 01:05:10
14-Sep-1984 12:23:47

VAX-11 Bliss-32 V4.0-742
DISK\$VMSMASTER:[EDT.SRC]LXCOM.BLI;1 Page 7
(3)

```

285      0855      3      EDT$$TY_CMD ();
286      0856      END;
287      0857
288      0858      [COM_NULL] :
289      0859      BEGIN
290      0860      EDT$$STOP_WKINGMSG ();
291      0861      EDT$$NULL_CMD ();
292      0862      END;
293      0863
294      0864      [COM_FIND] :
295      0865      BEGIN
296      0866      EDT$$G_RNG_FRSTLN = 1;
297      0867      EDT$$CPY_MEM (POS_SIZE, .EDT$$A_CUR_BUF, EDT$$Z_RNG_ORIGPOS);
298      0868      EDT$$RNG_REPOS (.EDT$$A_EXE_CURCMD [RANGE1]);
299      0869      END;
300      0870
301      0871      [COM_SUBS] :
302      0872      BEGIN
303      0873      EDT$$LN_SUBCMD ();
304      0874      END;
305      0875
306      0876      [COM_EXIT] :
307      0877      BEGIN
308      0878      EDT$$EXI_CMD ();
309      0879      END;
310      0880
311      0881      [COM_REPLACE] :
312      0882      BEGIN
313      0883
314      0884      IF EDT$$DEL_LNS () THEN EDT$$INS_TXT ();
315      0885
316      0886      END;
317      0887
318      0888      [COM_INCLUDE] :
319      0889      BEGIN
320      0890      EDT$$INCL_CMD ();
321      0891      END;
322      0892
323      0893      [COM_WRITE] :
324      0894      BEGIN
325      0895      EDT$$G_EXE_SBITS<OPB_STAY> = 1;      ! write never changes the position
326      0896      EDT$$WR_CMD ();
327      0897      END;
328      0898
329      0899      [COM_SUBS_NEXT] :
330      0900      BEGIN
331      0901      EDT$$SUB_NXTCMD ();
332      0902      END;
333      0903
334      0904      [COM_HELP] :
335      0905      BEGIN
336      0906      EDT$$SC_NONREVID ();
337      0907      EDT$$OUT_HLP (.EDT$$A_EXE_CURCMD [FILSPEC], .EDT$$A_EXE_CURCMD [FSPCLN], 1);
338      0908      EDT$$G_TXT_ONSCR = 1;
339      0909      END;
340      0910
341      0911      2      [COM_SET] :
```

```
342 0912 BEGIN
343 0913 EDT$$SET_CMD ();
344 0914 END;
345 0915
346 0916 [COM SHOW] :
347 0917 BEGIN
348 0918 EDT$$SHW_CMD ();
349 0919 END;
350 0920
351 0921 [COM CHANGE] :
352 0922 BEGIN
353 0923
354 0924 + Position to the first line of the specified range
355 0925 - and set the current mode to change mode.
356 0926
357 0927 EDT$$G_RNG_FRSTLN = 1;
358 0928 EDT$$CPY_MEM (POS_SIZE, .EDT$$A_CUR_BUF, EDT$$Z_RNG_ORIGPOS);
359 0929
360 0930 IF EDT$$RNG_REPOS (.EDT$$A_EXE_CURCMD [RANGE1]) THEN EDT$$G_EDIT_MOD = CHANGE_MODE;
361 0931
362 0932 END;
363 0933
364 0934 [COM MOVE] :
365 0935 BEGIN
366 0936 EDT$$MOVCPY_CMD (1);
367 0937 END;
368 0938
369 0939 [COM COPY] :
370 0940 BEGIN
371 0941 EDT$$MOVCPY_CMD (0);
372 0942 END;
373 0943
374 0944 [COM DEFINE] :
375 0945 BEGIN
376 0946 EDT$$DEFK_CMD ();
377 0947 END;
378 0948
379 0949 [COM PRINT] :
380 0950 BEGIN
381 0951 EDT$$G_EXE_SBITS<OPB_STAY> = 1; ! print never changes the position
382 0952 EDT$$PRNT_CMD ();
383 0953 END;
384 0954
385 0955 [COM RESEQ] :
386 0956 BEGIN
387 0957 EDT$$RSEQ_CMD ();
388 0958 END;
389 0959
390 0960 [COM TADJ] :
391 0961 BEGIN
392 0962 EDT$$TSADJ_CMD ();
393 0963 END;
394 0964
395 0965 [COM FILL] :
396 0966 BEGIN
397 0967 EDT$$FILL_CMD ();
398 0968 END;
```


EDT\$LXCOM
V04-000

EDT\$LXCOM - execute a line-mode command
EDT\$\$LNM_CMD - execute a line-mode command

J 3
16-Sep-1984 01:05:10
14-Sep-1984 12:23:47

VAX-11 Bliss-32 V4.0-742
DISK\$VMSMASTER:[EDT.SRC]LXCOM.BLI;1

Page 9
(3)

```

: 399      0969 2
: 400      0970
: 401      0971 [COM DEF MAC] :
: 402      0972     BEGIN
: 403      0973     EDT$$DEFM_CMD ();
: 404      0974     END;
: 405      0975 [COM MAC CALL] :
: 406      0976     BEGIN
: 407      0977     EDT$$MAC_CALL (.EDT$$A_EXE_CURCMD [RANGE1]);
: 408      0978     END;
: 409      0979
: 410      0980 [COM CLEAR] :
: 411      0981     BEGIN
: 412      0982     EDT$$CLR_CMD ();
: 413      0983     END;
: 414      0984
: 415      0985 [OUTRANGE] :
: 416      0986     BEGIN
: 417      0987     ASSERT (0);
: 418      0988     END;
: 419      0989     TES;
: 420      0990
: 421      0991 IF .EDT$$G_EXITD
: 422      0992 THEN
: 423      0993
: 424      0994     IF .EDT$$G_EXE_SBITS<OPB_SAVE> THEN EDT$$G_EXITD = 3;
: 425      0995
: 426      0996 IF .EDT$$G_RCOV_MOD THEN EDT$$G_EXITD = 0;
: 427      0997
: 428      0998 END;

```

! of routine EDT\$\$LNM_CMD

```

:
: .TITLE EDT$LXCOM EDT$LXCOM - execute a line-mode comma
: .IDENT \V04-000\
: .PSECT _EDT$CODE,NOWRT, SHR, PIC,2
00 10 00 40 00 02 00 00 00 50 02 00 22 00 00 00000 P.AAA: .BYTE 0, 0, 34, 0, 2, 80, 0, 0, 0, 2, 0, 64, 0, - :
: 00 00 00 00 08 00 00 10 84 0E 00 0000F 16, 0, 0, 14, -124, 16, 0, 0, 8, 0, 0, 0, - :
: 0

```

```

OPT_TABLE= P.AAA
.EXTRN EDT$$SC_NONREVID
.EXTRN EDT$$STOP_WKINGMSG
.EXTRN EDT$$CLR_CMD, EDT$$DEFK_CMD
.EXTRN EDT$$DEFM_CMD, EDT$$DEL_CMD
.EXTRN EDT$$MAC_CALL, EDT$$EXI_CMD
.EXTRN EDT$$FILC_CMD, EDT$$FMT_CRLF
.EXTRN EDT$$FMT_MSG, EDT$$OUT_RLP
.EXTRN EDT$$INCC_CMD, EDT$$INS_CMD
.EXTRN EDT$$DEL_CNS, EDT$$INS_TXT
.EXTRN EDT$$MOVCPY_CMD
.EXTRN EDT$$NULL_CMD, EDT$$PRNT_CMD
.EXTRN EDT$$RNG_REPOS, EDT$$RSEQ_CMD
.EXTRN EDT$$SET_CMD, EDT$$SHW_CMD
.EXTRN EDT$$LN_SUBCMD, EDT$$SOB_NXTCMD

```

```
                                OFFC 00000
5B 00000000G 00 9E 00002
5A 00000000G 00 9E 00009
59 00000000G 00 9E 00010
58 00000000G 00 9E 00017
57 00000000G 00 9E 0001E
68      04 AC D0 00025
50      68 D0 00029
01      60 91 0002C
      03 13 0002F
6B      00 FB 00031
50      68 D0 00034 1$:
6A      14 A0 D0 00037
51      6A D0 0003B
      29 13 0003E
50      01 A0 9A 00040
50      9E AF 40 9A 00044
50      50 D2 00049
50      04 A1 D3 0004C
      0E 13 00050
00000000G 00 00000000G 8F DD 00052
      01 FB 00058
      04 0005F
50      6A D0 00060 2$:
67      04 A0 D0 00063
      02 11 00067
      67 D4 00069 3$:
00000000G 00 D4 0006B 4$:
56      68 D0 00071
00      01 A6 8F 00074
0116      006E 00079 5$:
00C5      004E 00081
0039      0159 0045 00089
010D      0104 0166 00B2 00091
00DB      00CE 0057 00A0 00099
0178      016F 0196 00E4 000A1
      018A 0181 000A9

.ENTRY EDT$$LNM_CMD, Save R2,R3,R4,R5,R6,R7,R8,R9,-; 0686
MOVAB EDT$INTER_ERR, R11
MOVAB EDT$$Z_EXE_SBLK, R10
MOVAB EDT$G_EXITD, R9
MOVAB EDT$A_EXE_CURCMD, R8
MOVAB EDT$G_EXE_SBITS, R7
MOVL COM_START, EDT$A_EXE_CURCMD 0807
MOVL EDT$A_EXE_CURCMD, R0 0811
CMPB (R0), #1
BEQL 1$
CALLS #0, EDT$INTER_ERR
MOVL EDT$A_EXE_CURCMD, R0 0812
MOVL 20(R0), EDT$$Z_EXE_SBLK
MOVL EDT$$Z_EXE_SBLK, R1 0814
BEQL 3$
MOVZBL 1(R0), R0 0818
MOVZBL OPT_TABLE[R0], R0
MCOML R0, R0
BITL 4(R1), R0
BEQL 2$
PUSHL #EDT$ INVOPCOM 0821
CALLS #1, EDT$FMT_MSG 0820
RET 0825
MOVL EDT$$Z_EXE_SBLK, R0
MOVL 4(R0), EDT$G_EXE_SBITS
BRB 4$ 0814
CLRL EDT$G_EXE_SBITS 0828
CLRL EDT$G_EXE_QRYQUIT 0830
MOVL EDT$A_EXE_CURCMD, R6 0832
CASEB 1(R6), #0, #25
.WORD 10$-5$, -
      26$-5$, -
      30$-5$, -
      32$-5$, -
      8$-5$, -
      13$-5$, -
      11$-5$, -
      17$-5$, -
      7$-5$, -
      29$-5$, -
      34$-5$, -
      6$-5$, -
      15$-5$, -
      35$-5$, -
```


EDTSLXCOM
V04-000

EDTSLXCOM - execute a line-mode command
EDT\$\$LNM_CMD - execute a line-mode command

L 3
16-Sep-1984 01:05:10
14-Sep-1984 12:23:47

VAX-11 Bliss-32 V4.0-742
DISK\$VMSMASTER:[EDT.SRC]LXCOM.BLI;1

Page 11
(3)

```

23$-5$,-
24$-5$,-
12$-5$,-
9$-5$,-
19$-5$,-
20$-5$,-
22$-5$,-
43$-5$,-
36$-5$,-
37$-5$,-
39$-5$,-
41$-5$,-
6B      00 FB 000AD  CALLS #0, EDT$$INTER_ERR      0987
77      11 000B0  BRB      14$      0832
69      01 DO 000B2 6$:    MOVL #1, EDT$$G_EXITD      0837
00000000G 00      00 FB 000B5  CALLS #0, EDT$$FMT_CRLF      0838
7E      11 000BC  BRB      16$      0832
00000000G 00      00 FB 000BE 7$:    CALLS #0, EDT$$INS_CMD      0843
7E      11 000C5  BRB      18$      0832
00000000G 00      00 FB 000C7 8$:    CALLS #0, EDT$$DEL_CMD      0848
75      11 000CE  BRB      18$      0832
00000000G 00      00 FB 000D0 9$:    CALLS #0, EDT$$STOP_WKINGMSG      0853
00000000G 00      00 FB 000D7  CALLS #0, EDT$$SC_NONREVID      0854
00000000G 00      00 FB 000DE  CALLS #0, EDT$$TY_CMD      0855
74      11 000E5  BRB      21$      0832
00000000G 00      00 FB 000E7 10$:   CALLS #0, EDT$$STOP_WKINGMSG      0860
00000000G 00      00 FB 000EE  CALLS #0, EDT$$NULL_CMD      0861
64      11 000F5  BRB      21$      0832
00000000G 00      01 DO 000F7 11$:   MOVL #1, EDT$$G_RNG_FRSTLN      0866
50      00 DO 000FE  MOVL EDT$$A_CUR_BUF, R0      0867
00000000G 00      0E 28 00105  MOV C3 #14, (R0), EDT$$Z_RNG_ORIGPOS
60      04 A6 DD 0010D  PUSHL 4(R6)      0868
00000000G 00      01 FB 00110  CALLS #1, EDT$$RNG_REPOS      0832
74      11 00117  BRB      25$      0873
00000000G 00      00 FB 00119 12$:   CALLS #0, EDT$$LN_SUBCMD      0832
6B      11 00120  BRB      25$      0878
00000000G 00      00 FB 00122 13$:   CALLS #0, EDT$$EXI_CMD      0832
62      11 00129 14$:   BRB      25$      0884
00000000G 00      00 FB 0012B 15$:   CALLS #0, EDT$$DEL_LNS      0832
7A      50 E9 00132  BLBC R0, 27$
00000000G 00      00 FB 00135  CALLS #0, EDT$$INS_TXT      0832
7A      11 0013C 16$:   BRB      28$      0890
00000000G 00      00 FB 0013E 17$:   CALLS #0, EDT$$INCL_CMD      0832
71      11 00145 18$:   BRB      28$      0895
00000000G 00      8F 88 00147 19$:   BIS B2 #128, EDT$$G_EXE_SBITS      0896
7C      11 00152  CALLS #0, EDT$$WR_CMD      0832
00000000G 00      00 FB 00154 20$:   CALLS #0, EDT$$SUB_NXTCMD      0901
73      11 0015B 21$:   BRB      33$      0832
00000000G 00      00 FB 0015D 22$:   CALLS #0, EDT$$SC_NONREVID      0906
01      DD 00164  PUSHL #1      0907
50      68 DO 00166  MOVL EDT$$A_EXE_CURCMD, R0
7E      A0 7D 00169  MOVQ 8(R0), -(SP)
00000000G 00      03 FB 0016D  CALLS #3, EDT$$OUT_HLP
00000000G 00      01 DO 00174  MOVL #1, EDT$$G_TXT_ONSCR
7B      11 0017B 38$
00000000G 00      00 FB 0017D 23$:   CALLS #0, EDT$$SET_CMD      0908
                                0832
                                0913
```

ED
VO

EDT\$LXCOM
V04-000

EDT\$LXCOM - execute a line-mode command
EDT\$\$LNM_CMD - execute a line-mode command

M 3
16-Sep-1984 01:05:10
14-Sep-1984 12:23:47

VAX-11 Bliss-32 V4.0-742
DISK\$VMSMASTER:[EDT.SRC]LXCOM.BLI;1

Page 12
(3)

00000000G	00	7B 11 00184	BRB	40\$		0832
		00 FB 00186 24\$:	CALLS	#0, EDT\$\$SHW_CMD		0918
00000000G	00	7E 11 0018D 25\$:	BRB	42\$		0832
		01 D0 0018F 26\$:	MOVL	#1, EDT\$\$G_RNG_FRSTLN		0927
00000000G	50 00000000G	00 D0 00196	MOVL	EDT\$\$A_CUR_BUF, R0		0928
		60 0E 28 0019D	MOVCL	#14, (R0), EDT\$\$Z_RNG_ORIGPOS		
	04	A6 DD 001A5	PUSHL	4(R6)		0930
00000000G	00	01 FB 001A8	CALLS	#1, EDT\$\$RNG_REPOS		
		64 50 E9 001AF 27\$:	BLBC	R0, 44\$		
	00000000G	00 D4 001B2	CLRL	EDT\$\$G_EDIT_MOD		
		5C 11 001B8 28\$:	BRB	44\$		0832
		01 DD 001BA 29\$:	PUSHL	#1		0936
		02 11 001BC	BRB	31\$		
		7E D4 001BE 30\$:	CLRL	-(SP)		0941
00000000G	00	01 FB 001C0 31\$:	CALLS	#1, EDT\$\$MOVCPY_CMD		
		4D 11 001C7	BRB	44\$		0832
00000000G	00	00 FB 001C9 32\$:	CALLS	#0, EDT\$\$DEFK_CMD		0946
		44 11 001D0 33\$:	BRB	44\$		0832
	67 80	8F 88 001D2 34\$:	BISB2	#128, EDT\$\$G_EXE_SBITS		0951
00000000G	00	00 FB 001D6	CALLS	#0, EDT\$\$PRNT_CMD		0952
		37 11 001DD	BRB	44\$		0832
00000000G	00	00 FB 001DF 35\$:	CALLS	#0, EDT\$\$RSEQ_CMD		0957
		2E 11 001E6	BRB	44\$		0832
00000000G	00	00 FB 001E8 36\$:	CALLS	#0, EDT\$\$TSADJ_CMD		0962
		25 11 001EF	BRB	44\$		0832
00000000G	00	00 FB 001F1 37\$:	CALLS	#0, EDT\$\$FILL_CMD		0967
		1C 11 001F8 38\$:	BRB	44\$		0832
00000000G	00	00 FB 001FA 39\$:	CALLS	#0, EDT\$\$DEFM_CMD		0972
		13 11 00201 40\$:	BRB	44\$		0832
	04	A6 DD 00203 41\$:	PUSHL	4(R6)		0977
00000000G	00	01 FB 00206	CALLS	#1, EDT\$\$MAC_CALL		
		07 11 0020D 42\$:	BRB	44\$		0832
00000000G	00	00 FB 0020F 43\$:	CALLS	#0, EDT\$\$CLR_CMD		0982
		69 E9 00216 44\$:	BLBC	EDT\$\$G_EXITD, 45\$		0991
03		67 06 E1 00219	BBC	#6, EDT\$\$G_EXE_SBITS, 45\$		0994
		69 03 D0 0021D	MOVL	#3, EDT\$\$G_EXITD		
	02 00000000G	00 E9 00220 45\$:	BLBC	EDT\$\$G_RCOV_MOD, 46\$		0996
		69 D4 00227	CLRL	EDT\$\$G_EXITD		
		04 00229 46\$:	RET			0998

; Routine Size: 554 bytes, Routine Base: _EDT\$CODE + 001A

: 429 0999 1
: 430 1000 1 !<BLF/PAGE>

ED
VO

EDT\$LXCOM
V04-000

EDT\$LXCOM - execute a line-mode command
EDT\$\$LNM_CMD - execute a line-mode command

N 3
16-Sep-1984 01:05:10
14-Sep-1984 12:23:47

VAX-11 Bliss-32 V4.0-742
DISK\$VMSMASTER:[EDT.SRC]LXCOM.BLI;1

Page 13
(4)

: 432
: 433
: 434
1001 1 END
1002 1
1003 0 ELUDOM

! of module EDT\$LXCOM

EDT\$\$LNM_CMD_NOOVERLAY REF==
EDT\$\$LNM_CMD

PSECT SUMMARY

Name	Bytes	Attributes
_EDT\$CODE	580	NOVEC,NOWRT, RD , EXE, SHR, LCL, REL, CON, PIC,ALIGN(2)

Library Statistics

File	----- Total	Symbols Loaded	----- Percent	Pages Mapped	Processing Time
_\$255\$DUA28:[EDT.SRC]EDT.L32;1	377	122	32	40	00:00.2
_\$255\$DUA28:[EDT.SRC]PSECTS.L32;1	2	1	50	7	00:00.1

COMMAND QUALIFIERS

BLISS/CHECK=(FIELD,INITIAL,OPTIMIZE)/NOTRACEBACK/LIS=LIS\$:LXCOM/OBJ=OBJ\$:LXCOM MSRC\$:LXCOM.BLI/UPDATE=(ENH\$:LXCOM)

: Size: 554 code + 26 data bytes
: Run Time: 00:25.1
: Elapsed Time: 00:29.9
: Lines/CPU Min: 2396
: Lexemes/CPU-Min: 8454
: Memory Used: 160 pages
: Compilation Complete

0137

DIGITAL EQUIPMENT CORPORATION
CONFIDENTIAL AND PROPRIETARY